

Your Digital Download Package will contain:

- CamSlicer Software (Mac only)
- Instruction Documents

You will need to provide:

- Username / Password, API Key, Slicer ID (sent by email from Vuuzle team)
- MacBook Pro (core i7, 16 gigs ram, recent OS)
- Hardwired Internet connection (WiFi will not work)
- Content to be streamed live to Vuuzle platform



1


Run the upLynk CamSlicer software on your Mac.

Use information provided by Vuuzle to complete the following fields:

- Username / Password
- API Key
- Slicer ID

NOTE: Make sure the information is EXACT, no spaces in front or or in back of words.

Click "Sign In" Button.



2

If you're logged in correctly - the "Select Event" screen will appear.


There will be a series of events in "Pre-Event" status. You may be able to see other people's events.

You need to choose an available event that is assigned to YOUR account for your event to appear on your channel.

Example: If you're Bob Smith, there will be a series of events like: bsmith_live1, bsmith_live2, etc.

Once you have "used" an event (live webcast) it will no longer appear in your list when you login.

Highlight your event and click "Next".



3

Setup your upLynk CameraSlicer:

MOST BASIC SETUP:


Video Source: Your laptop webcam

Video Input Setting: Default

Audio Source: Your laptop microphone

Streaming Quality: 700Kbps (DO NOT CHANGE)

This will allow you to stream live video and audio from your laptop to Vuuzle TV.




4

Once you have chosen your Video and Audio inputs - you will see the video and be able to view audio levels to the right of the video.

If you do not see video or audio indicators - DO NOT GO LIVE.

Other devices on your laptop may appear in the video & audio source dropdowns (See advanced documentation).

If you are satisfied with your Video & Audio input - click on the "Begin Event" button. This will start your live stream to Vuuzle TV.




5

NOTE: Once you have started your live event, there is a 60-90 second delay before your video appears on the Vuuzle TV platform. Be patient.

Make sure your CameraSlicer shows green check marks next to the "Computer" and "Internet" status indicators.

In the box marked "Ad Break" put 30 seconds (or other amount) in the right hand box. When you wish to insert an Ad Break, press the "Begin" button.




6

Understanding Ad Breaks:

While you are in an ad break video and audio on your live event will NOT be seen or recorded.

You must MANUALLY stop the ad break by pressing the “End” button regardless of the time you entered for the ad break.


If you do not “End” your ad break - your webcast will NOT continue.



7

To end your live event, click the “Finish Event” button at the bottom of CameraSlicer.

DO NOT CLOSE CameraSlicer - a notice will appear when your event has finished and it’s safe to close the CameraSlicer.



Additional Information:

This is the simplest usage of upLynk CameraSlicer. Please see our [Advanced Documentation](#) to understand how CameraSlicer can achieve broadcast quality events for your team.

Remember: CameraSlicer “sees” webcam devices but can be used as a final output device for most standard broadcast devices capable of HD-SDI or HDMI output including: Tricasters, Wirecast, OBS and Blackmagic Design Devices.

Contact your team at Vuuzle TV for more information.